

opendir/readdir(3)

opendir/readdir(3)

NAME

opendir – open a directory / readdir – read a directory

SYNOPSIS

```
#include <sys/types.h>
```

```
#include <dirent.h>
```

```
DIR *opendir(const char *name);
```

```
struct dirent *readdir(DIR *dir);
```

```
int readdir_r(DIR *dirp, struct dirent *entry, struct dirent **result);
```

DESCRIPTION

The `opendir()` function opens a directory stream corresponding to the directory *name*, and returns a pointer to the directory stream. The stream is positioned at the first entry in the directory.

RETURN VALUE

The `opendir()` function returns a pointer to the directory stream or `NULL` if an error occurred.

DESCRIPTION readdir

The `readdir()` function returns a pointer to a dirent structure representing the next directory entry in the directory stream pointed to by *dir*. It returns `NULL` on reaching the end-of-file or if an error occurred.

DESCRIPTION readdir_r

The `readdir_r()` function initializes the structure referenced by *entry* and stores a pointer to this structure in *result*. On successful return, the pointer returned at *result* will have the same value as the argument *entry*. Upon reaching the end of the directory stream, this pointer will have the value `NULL`.

The data returned by `readdir()` is overwritten by subsequent calls to `readdir()` for the same directory stream.

The *dirent* structure is defined as follows:

```
struct dirent {
    long      d_ino;           /* inode number */
    off_t     d_off;         /* offset to the next dirent */
    unsigned short d_reclen; /* length of this record */
    unsigned char  d_type;   /* type of file */
    char          d_name[256]; /* filename */
};
```

RETURN VALUE

The `readdir()` function returns a pointer to a dirent structure, or `NULL`, if an error occurs or end-of-file is reached.

`readdir_r()` returns 0 if successful or an error number to indicate failure.

ERRORS

EACCES Permission denied.

ENOENT

Directory does not exist, or *name* is an empty string.

ENOTDIR

name is not a directory.

feof/ferror/fileno(3)

feof/ferror/fileno(3)

NAME

clearerr, feof, ferror, fileno – check and reset stream status

SYNOPSIS

```
#include <stdio.h>
```

```
void clearerr(FILE *stream);
```

```
int feof(FILE *stream);
```

```
int ferror(FILE *stream);
```

```
int fileno(FILE *stream);
```

DESCRIPTION

The function `clearerr()` clears the end-of-file and error indicators for the stream pointed to by *stream*.

The function `feof()` tests the end-of-file indicator for the stream pointed to by *stream*, returning non-zero if it is set. The end-of-file indicator can only be cleared by the function `clearerr()`.

The function `ferror()` tests the error indicator for the stream pointed to by *stream*, returning non-zero if it is set. The error indicator can only be reset by the `clearerr()` function.

The function `fileno()` examines the argument *stream* and returns its integer descriptor.

For non-locking counterparts, see `unlocked_stdio(3)`.

ERRORS

These functions should not fail and do not set the external variable *errno*. (However, in case `fileno()` detects that its argument is not a valid stream, it must return `-1` and set *errno* to `EBADF`.)

CONFORMING TO

The functions `clearerr()`, `feof()`, and `ferror()` conform to C89 and C99.

SEE ALSO

`open(2)`, `fdopen(3)`, `stdio(3)`, `unlocked_stdio(3)`

fopen/fdopen(3)

fopen/fdopen(3)

fgets(3)

fgets(3)

NAME

fopen, fdopen, fileno – stream open functions

SYNOPSIS

```
#include <stdio.h>
```

```
FILE *fopen(const char *path, const char *mode);  
FILE *fdopenint (files, const char *mode);  
int fileno(FILE *stream);
```

DESCRIPTION

The **fopen** function opens the file whose name is the string pointed to by *path* and associates a stream with it.

The argument *mode* points to a string beginning with one of the following sequences (Additional characters may follow these sequences):

r Open text file for reading. The stream is positioned at the beginning of the file.

r+ Open for reading and writing. The stream is positioned at the beginning of the file.

w Truncate file to zero length or create text file for writing. The stream is positioned at the beginning of the file.

w+ Open for reading and writing. The file is created if it does not exist, otherwise it is truncated. The stream is positioned at the beginning of the file.

a Open for appending (writing at end of file). The file is created if it does not exist. The stream is positioned at the end of the file.

a+ Open for reading and appending (writing at end of file). The file is created if it does not exist. The stream is positioned at the end of the file.

The **fdopen** function associates a stream with the existing file descriptor, *files*. The *mode* of the stream (one of the values "r", "r+", "w", "w+", "a", "a+") must be compatible with the mode of the file descriptor. The file position indicator of the new stream is set to that belonging to *files*, and the error and end-of-file indicators are cleared. Modes "w" or "w+" do not cause truncation of the file. The file descriptor is not dup'ed, and will be closed when the stream created by **fdopen** is closed. The result of applying **fdopen** to a shared memory object is undefined.

The function **fileno()** examines the argument *stream* and returns its integer descriptor.

RETURN VALUE

Upon successful completion **fopen**, **fdopen** and **freopen** return a **FILE** pointer. Otherwise, **NULL** is returned and the global variable *errno* is set to indicate the error.

ERRORS

EINVAL

The *mode* provided to **fopen**, **fdopen**, or **freopen** was invalid.

The **fopen**, **fdopen** and **freopen** functions may also fail and set *errno* for any of the errors specified for the routine **malloc(3)**.

The **fdopen** function may also fail and set *errno* for any of the errors specified for the routine **open(2)**.

The **fdopen** function may also fail and set *errno* for any of the errors specified for the routine **fcntl(2)**.

SEE ALSO

open(2), **fclose(3)**, **fileno(3)**

NAME

gets, fgets – get a string from a stream
fputs, puts – output of strings

SYNOPSIS

```
#include <stdio.h>  
char *gets(char *s);  
char *fgets(char *s, int n, FILE *stream);  
int fputs(const char *s, FILE *stream);  
int puts(const char *s);
```

DESCRIPTION gets/fgets

The **gets()** function reads characters from the standard input stream (see **intro(3)**), **stdin**, into the array pointed to by *s*, until a newline character is read or an end-of-file condition is encountered. The newline character is discarded and the string is terminated with a null character.

The **fgets()** function reads characters from the *stream* into the array pointed to by *s*, until *n*–1 characters are read, or a newline character is read and transferred to *s*, or an end-of-file condition is encountered. The string is then terminated with a null character.

When using **gets()**, if the length of an input line exceeds the size of *s*, indeterminate behavior may result. For this reason, it is strongly recommended that **gets()** be avoided in favor of **fgets()**.

RETURN VALUES

If end-of-file is encountered and no characters have been read, no characters are transferred to *s* and a null pointer is returned. If a read error occurs, such as trying to use these functions on a file that has not been opened for reading, a null pointer is returned and the error indicator for the stream is set. If end-of-file is encountered, the EOF indicator for the stream is set. Otherwise *s* is returned.

ERRORS

The **gets()** and **fgets()** functions will fail if data needs to be read and:

EOVERFLOW The file is a regular file and an attempt was made to read at or beyond the offset maximum associated with the corresponding *stream*.

DESCRIPTION puts/fputs

fputs() writes the string *s* to *stream*, without its trailing '\0'.

puts() writes the string *s* and a trailing newline to *stdout*.

Calls to the functions described here can be mixed with each other and with calls to other output functions from the **stdio** library for the same output stream.

RETURN VALUE

puts() and **fputs()** return a non - negative number on success, or **EOF** on error.

`pthread_create(pthread_t(3))` pthread_create(pthread_t(3))

NAME
pthread_create – create a new thread / pthread_exit – terminate the calling thread

SYNOPSIS
`#include <pthread.h>`

```
int pthread_create(pthread_t * thread, pthread_attr_t * attr, void * (*start_routine)(void *), void *
arg);
void pthread_exit(void *retval);
```

DESCRIPTION
`pthread_create` creates a new thread of control that executes concurrently with the calling thread. The new thread applies the function `start_routine` passing it `arg` as first argument. The new thread terminates either explicitly, by calling `pthread_exit(3)`, or implicitly, by returning from the `start_routine` function. The latter case is equivalent to calling `pthread_exit(3)` with the result returned by `start_routine` as exit code.

The `attr` argument specifies thread attributes to be applied to the new thread. See `pthread_attr_t(3)` for a complete list of thread attributes. The `attr` argument can also be `NULL`, in which case default attributes are used: the created thread is joinable (not detached) and has default (non real-time) scheduling policy.

`pthread_exit` terminates the execution of the calling thread. All cleanup handlers that have been set for the calling thread with `pthread_cleanup_push(3)` are executed in reverse order (the most recently pushed handler is executed first). Finalization functions for thread-specific data are then called for all keys that have non-`NULL` values associated with them in the calling thread (see `pthread_key_create(3)`). Finally, execution of the calling thread is stopped.

The `retval` argument is the return value of the thread. It can be consulted from another thread using `pthread_join(3)`.

RETURN VALUE

On success, the identifier of the newly created thread is stored in the location pointed by the `thread` argument, and a 0 is returned. On error, a non-zero error code is returned.

The `pthread_exit` function never returns.

ERRORS

EAGAIN
not enough system resources to create a process for the new thread.

EAGAIN
more than `PTHREAD_THREADS_MAX` threads are already active.

AUTHOR

Xavier Leroy <XavierLeroy@inria.fr>

SEE ALSO

`pthread_join(3)`, `pthread_detach(3)`, `pthread_attr_t(3)`

`stat(2)`

`stat(2)`

NAME
stat, fstat, lstat – get file status

SYNOPSIS
`#include <sys/types.h>`
`#include <sys/stat.h>`
`#include <unistd.h>`

```
int stat(const char *path, struct stat *buf);
int fstat(int fd, struct stat *buf);
int lstat(const char *path, struct stat *buf);
```

Feature Test Macro Requirements for glibc (see `feature_test_macros(7)`):

`!stat(): _BSD_SOURCE || _XOPEN_SOURCE >= 500`

DESCRIPTION
These functions return information about a file. No permissions are required on the file itself, but — in the case of `stat()` and `lstat()` — execute (search) permission is required on all of the directories in `path` that lead to the file.

`stat()` stats the file pointed to by `path` and fills in `buf`.

`lstat()` is identical to `stat()`, except that if `path` is a symbolic link, then the link itself is `stat-ed`, not the file that it refers to.

`fstat()` is identical to `stat()`, except that the file to be `stat-ed` is specified by the file descriptor `fd`.

All of these system calls return a `stat` structure, which contains the following fields:

```
struct stat {
    dev_t  st_dev; /* ID of device containing file */
    ino_t  st_ino; /* inode number */
    mode_t st_mode; /* protection */
    nlink_t st_nlink; /* number of hard links */
    uid_t  st_uid; /* user ID of owner */
    gid_t  st_gid; /* group ID of owner */
    dev_t  st_rdev; /* device ID (if special file) */
    off_t  st_size; /* total size, in bytes */
    blksize_t st_blksize; /* blocksize for the system I/O */
    btime_t st_btime; /* number of blocks allocated */
    time_t st_atime; /* time of last access */
    time_t st_mtime; /* time of last modification */
    time_t st_ctime; /* time of last status change */
};
```

The `st_dev` field describes the device on which this file resides.

The `st_rdev` field describes the device that this file (inode) represents.

The `st_size` field gives the size of the file (if it is a regular file or a symbolic link) in bytes. The size of a symlink is the length of the pathname it contains, without a trailing null byte.

The `st_blocks` field indicates the number of blocks allocated to the file, 512-byte units. (This may be smaller than `st_size/512` when the file has holes.)

The `st_blksize` field gives the "preferred" blocksize for efficient file system I/O. (Writing to a file in smaller chunks may cause an inefficient read-modify-rewrite.)

Not all of the Linux file systems implement all of the time fields. Some file system types allow mounting in such a way that file accesses do not cause an update of the *st_atime* field. (See "routine" in [mount\(8\)](#).)

The field *st_atime* is changed by file accesses, for example, by [execve\(2\)](#), [mknod\(2\)](#), [pipe\(2\)](#), [utime\(2\)](#) and [read\(2\)](#) (of more than zero bytes). Other routines, like [mmap\(2\)](#), may or may not update *st_atime*.

The field *st_mtime* is changed by file modifications, for example, by [mknod\(2\)](#), [truncate\(2\)](#), [utime\(2\)](#) and [write\(2\)](#) (of more than zero bytes). Moreover, *st_mtime* of a directory is changed by the creation or deletion of files in that directory. The *st_mtime* field is *not* changed for changes in owner, group, hard link count, or mode.

The field *st_ctime* is changed by writing or by setting inode information (i.e., owner, group, link count, mode, etc.).

The following POSIX macros are defined to check the file type using the *st_mode* field:

S_ISREG(m)	is it a regular file?
S_ISDIR(m)	directory?
S_ISCHR(m)	character device?
S_ISBLK(m)	block device?
S_ISFIFO(m)	FIFO (named pipe)?
S_ISLNK(m)	symbolic link? (Not in POSIX.1-1996.)
S_ISSOCK(m)	socket? (Not in POSIX.1-1996.)

RETURN VALUE

On success, zero is returned. On error, -1 is returned, and *errno* is set appropriately.

ERRORS

EACCES

Search permission is denied for one of the directories in the path prefix of *path*. (See also [path_resolution\(7\)](#).)

EBADF

fd is bad.

EFAULT

Bad address.

ELOOP

Too many symbolic links encountered while traversing the path.

ENAMETOOLONG

File name too long.

ENOENT

A component of the path *path* does not exist, or the path is an empty string.

ENOMEM

Out of memory (i.e., kernel memory).

ENOTDIR

A component of the path is not a directory.

SEE ALSO

[access\(2\)](#), [chmod\(2\)](#), [chown\(2\)](#), [fsstatat\(2\)](#), [readlink\(2\)](#), [utime\(2\)](#), [capabilities\(7\)](#), [symlink\(7\)](#)